Leica DISTO™ with Bluetooth Smart usage on Android 4.3 or higher

V 1.1 April 2014

- when it has to be **right**





Content

- Leica DISTO[™] devices
- Bluetooth compatibility
- Leica DISTO™ Bluetooth Smart
- Leica DISTO™ sketch for Android



The Leica DISTO™ devices with Bluetooth®





→ Requires Bluetooth® 4.0



Leica DISTO™ D3a BT (D330i) Bluetooth® 2.1

→ Requires SPP support





Leica DISTO™ D8 Bluetooth® 2.1

→ Requires SPP support





Leica DISTO™ D510 Bluetooth® Smart

→ Requires Bluetooth® 4.0





Leica DISTO™ D810 touch Bluetooth® Smart

→ Requires Bluetooth® 4.0



Overview DISTO™ compatibility

		Windows 7	Windows 8.1	Windows Mobile 6.5	Android 2.3.3	Android 4.3	ios ios
Leica DISTO™ D110 Bluetooth® 4.0			Leica DISTO™ transfer www.disto.com	-		Leica DISTO™ transfer BLE Leica DISTO™ sketch SCOR Play	Leica DISTO TM sketch Available on the App Store
Leica DISTO™ D3a BT Bluetooth® 2.1		Leica DISTO™ transfer	Leica DISTO™ transfer www.disto.com	Leica DISTO™ transfer PPC www.disto.com	Leica DISTO™ transfer Leica DISTO™ sketch act if on Google play	Leica DISTO™ transfer Leica DISTO™ sketch ett if ok Google play	
Leica DISTO™ D8 Bluetooth® 2.1	1 000 1 000 1 100 2 0 0 2 0 0 3 0 0 4 0 0 5 0 0 6 0 0 7 0 0 8 0 8	Leica DISTO™ transfer	Leica DISTO™ transfer www.disto.com	Leica DISTO™ transfer PPC www.disto.com	Leica DISTO™ transfer Leica DISTO™ sketch Ger II on Google play	Leica DISTO™ transfer Leica DISTO™ sketch act trok Google play	
Leica DISTO™ D510 Bluetooth® 4.0	1 2011 13 140 15 140 16 150 16 161 16 161 16 161 16 161 16 161 16 161		Leica DISTO™ transfer www.disto.com	-	-	Leica DISTO™ transfer BLE Leica DISTO™ sketch actificat Google play	Leica DISTO™ sketch Available on the App Store
Leica DISTO™ D810 touch Bluetooth® 4.0	2.19. 4.29. 3619.		Leica DISTO™ transfer Keypad mode *) www.disto.com	-	-	Leica DISTO™ transfer BLE Leica DISTO™ sketch act if on Google play	Leica DISTO™ sketch Keypad Mode *) Avoilable on the App Store

^{*)} DISTO™ connects as a keyboard and sends data right to cursor position in any application or software



Prolog

This presentation should provide further advice on how to use the Leica DISTO™ with Bluetooth® Smart. Also the corresponding Apps for Android are described in this document.



Leica DISTO™ Bluetooth Smart



Getting started

- when it has to be **right**





General Bluetooth® Smart

- Bluetooth® Smart is compatible with Bluetooth® 4.0 or Bluetooth® Smart Ready devices
- Bluetooth® Smart has very low power consumption why it is by default switched on



Leica DISTO™ D110 Bluetooth® Smart

- The Bluetooth® can be switched off and on at the Leica DISTO™ D110
- The Leica DISTO™ D110 only supports the connection to iOS or Android 4.3 Apps





Leica DISTO™ D510 Bluetooth® Smart

- The Bluetooth® can be switched off in the Settings of the Leica DISTO™ D510
- The Leica DISTO[™] D510 only supports the connection to iOS or Android 4.3 Apps







Press '=' to switch on or off



Leica DISTO™ D810 touch Bluetooth® Smart

The Bluetooth® can be switched off in the Settings of the Leica DISTO™ D810 touch














Leica DISTO™ D810 touch Bluetooth® Smart

The Leica DISTO™ D810 touch provides 3 different modes for use with Bluetooth®





Leica DISTO™ sketch

Android 4.3 or higher



Getting started

- when it has to be right





Leica DISTO™ sketch for Android 4.3 or higher Start App

- When using with Leica DISTO™ D810 touch we are recommending to use the App mode for Bluetooth®
- When using with Leica DISTO™ D810 touch it is required to set the Leica DISTO™ device Bluetooth® to unencrypted mode first. Otherwise the device will connect but it will not transfer measurement values!
 - This is not required for the Leica DISTO™ D510 or D110.













Leica DISTO™ sketch for Android 4.3 or higher Start App




Leica DISTO™ sketch for Android 4.3 or higher Start App – Connect Bluetooth®

Press if you want to start Scan for devices again












Leica DISTO™ sketch for Android 4.3 or higher Sketch layout Overview



Leica DISTO™ sketch for Android 4.3 or higher

Create new sketch



























Transfer area, volume or a slope









Leica DISTO™ sketch for Android 4.3 or higher Changing sketch name or deleting sketch





Leica DISTO™ sketch for Android 4.3 or higher Create new sketch with photo

















Leica DISTO™ sketch for Android 4.3 or higher Good to know

• The Leica DISTO™ device only sends the currently measured value. To send a result from the main line of the DISTO™ press the "=" key on the D810 touch or D510. For the D110 press the Bluetooth® key to send a result from the main line.



Press short to send the measurement value from the main line of the display (e.g. area)

- To send a value using a D3a BT or D8 with Bluetooth® 2.1 you need to press the Bluetooth® key
- If you like to transfer distance measurement values including the inclination you need to switch on the Level option in the Setting of your Leica DISTO™ device.







Leica DISTO™ D3a BT (D330i)

Leica DISTO™ D8

Leica DISTO™ D510 or D810 touch





Leica DISTO™ transfer

Android 4.3 or higher



Getting started

- when it has to be right





Leica DISTO™ transfer for Android 4.3 or higher Start App

- When using with Leica DISTO™ D810 touch we are recommending to use the App mode for Bluetooth®
- When using with Leica DISTO™ D810 touch it is required to set the Leica DISTO™ device Bluetooth® to unencrypted mode first. Otherwise the device will connect but it will not transfer measurement values!
 - This is not required for the Leica DISTO™ D510 or D110.












Leica DISTO™ transfer for Android 4.3 or higher Start App – Connect Bluetooth®

Press if you want to start Scan for devices again











Press Menu to get pop-up



Leica DISTO™ transfer for Android 4.3 or higher Transfer layout Overview

